

VAPolyFM

Hybrid Synthesizer



User Guide

Version 1.0

Table of Contents

Introduction	15
Privacy Settings	15
Main Features	15
System Requirements	15
Use as Stand Alone	16
Use as AudioUnit Extension (AUv3)	16
Factory Preset	16
User Preset	16
State Recovery	16
About MIDI Latency	16
User Interface	17
Tool Bar	19
FM Synth	21
Global	21
Operator	22
Operator	23
Global	24
VA Synth and Effects	25
Oscillator 1	25
Oscillator 2 and LFO1	26
Mixer, Effect Send and LFO2	27
LPF, HPF and Env1	28
AMP, FM AMP and Env2	29
Global, ARP and VCF	30
KBD Control Routing	31
DLY (Delay)	32
C/F (Chorus / Flanger)	33
REV (Reverb)	34
EQ (3 Band EQ / Effect Mixer)	35

CMP (Compressor)	36
Keyboard	37
Visualizer	38
Sequencer	40
Clip Editor	41
Piano Roll Editor	42
Parameter Automation Editor	43
Synthesizer	44
Block diagram	44
Control Signal & MIDI Flow	44
FM Synthesizer	45
Block diagram FM Synthesizer	45
Operator	46
Power Switch	46
Coarse	46
Level	46
Mode	46
Fine	46
Detune	46
EG T1...T4	47
EG L1...L4	47
Key Follow	47
EG Velocity	47
AM Depth	47
PM Depth	47
Key Tracking Break Point	47
Key Tracking Left Depth	47
Key Tracking Left Curve	47
Key Tracking Right Depth	47
Key Tracking Right Curve	47

Five Stage Envelope Generator	48
Key Tracking	48
Global	49
Algorithm	49
Feedback	49
OSC Key Sync	49
Transpose	49
Master Tune	49
Pitch EG T1...T4	50
Pitch EG L1...L4	50
LFO Speed	50
LFO Key Sync	50
LFO Wave	50
LFO Delay	50
LFO PMD	50
LFO AMD	50
PB Range	50
PB Step	50
MW Range	50
MW Assign	50
AT Range	50
AT Assign	50
VA Synthesizer	51
Block diagram VA Synthesizer	51
Oscillator 1	52
Tune	52
Shape	52
Sync	52
PW (Pulse Width)	52
Oscillator 2	53

Tune	53
Fine (Fine Tune)	53
Shape	53
KBD (Keyboard) SW	53
LFO SW	53
PW (Pulse Width)	53
Oscillator Modulation	54
LFO Modulation	54
FM LFO (LFO to Frequency)	54
Shape LFO (LFO to Shape)	54
PW LFO (LFO to Pulse Width)	54
Frequency Modulation Type	54
LFO Source	54
Envelope & Cross Modulation	55
FM Env (Envelope to Frequency)	55
Shape Env (Envelope to Shape)	55
PW Env (Envelope to Pulse Width)	55
FM XMOD (XMOD to Frequency)	55
Shape XMOD (XMOD to Shape)	55
Env Source	55
Mixer	56
FM	56
OSC1, OSC2	56
Sub (Sub Oscillator Level)	56
Ring (Ring Modulation Level)	56
Noise (Noise Level)	56
Low Pass Filter	57
Cutoff	57
Resonance	57
Env Mod (Envelope Modulation Intensity)	57

LFO Mod (LFO Modulation Intensity)	57
Key Follow	57
VCF Slope	57
High Pass filter	58
Cutoff	58
Resonance	58
Env Mod Int (Envelope Modulation Intensity)	58
LFO Mod Int (LFO Modulation Intensity)	58
Key Follow	58
VCF Setting	59
LP Env Source	59
LP LFO Source	59
HP Env Source	59
HP LFO Source	59
AMP (Amplifier)	60
Volume	60
LFO PAN (Pan Modulation Intensity)	60
LFO AM (Amplitude Modulation Intensity)	60
Gate/Env(ADSR)	60
Pan Source	60
AM Source	60
ADSR (Envelope Generator)	61
Attack	61
Decay	61
Sustain	61
Release	61
Delay	61
Key Follow	61
LFO	62
Tune	62

Shape	62
Sync	62
Key Trg (Key Re-Trigger)	62
AM Env	62
Effect Send	63
Delay Send	63
Delay Pre/Post	63
C/F Send	63
C/F Pre/Post	63
Reverb Send	63
Reverb Pre/Post	63
Effect Output Mixer	64
Delay Level	64
Delay Bypass	64
C/F Level	64
C/F Bypass	64
Reverb Level	64
Reverb Bypass	64
ARP (Arpeggio)	65
Arp Rate	65
Arp Pattern	65
Arp Switch	65
Arp Sync	65
Global	66
Env1 & Env2 KBD Velocity	66
Stereo	66
Unison	66
Voices	66
Glide Time	66
Master Output	67

Volume	67
Pan	67
Mute	67
KBD Control Routing	68
Effects	69
Delay	69
Signal Flow	69
Delay Time	69
Regeneration	69
Modulation	69
Chorus / Flanger	70
Signal Flow	70
Input Signal Level	70
Effect Type	70
Modulation Speed	70
Modulation Width	70
LFO Shape	70
Stereo Width	70
Regeneration	70
Filters	71
Reverb	72
Signal Flow	72
Input Filter	72
Pre Delay	72
Modulation Speed	72
Modulation Width	72
Size and Decay	72
Damping	72
Output Filter	72
Early / Late Mix	73

Equalizer	74
Low Shelving	74
Mid Peak / Notch	74
High Shelving	74
Compressor	75
Overview	75
Threshold and Ratio	75
Attack and Release	76
Side Chain High Pass Filter	78
Makeup Gain	78
Gain Reduction Meter	78
Input Gain	78
Dry / Wet	78
Peak Limiter	79
Keyboard	80
Select Keyboard	80
Select Key Range	80
Use Modulation Wheel	80
Use Pitch Wheel	80
Set Velocity	81
Use Key Hold	81
Show Double Keyboard	81
Sequencer	82
Clip Editor	83
Load Clip	83
Play/Stop Clip	83
Edit Piano Roll	83
Add edit button	83
Set Loop Mode	83
Piano Roll Editor	84

Select Time Range and Loop Length	84
Select Note Range	84
Add Note	84
Delete Note	84
Scale Menu	84
Edit Menu	84
Chromatic Scale	85
Heptatonic Scale	85
Root Key	85
Set Length	86
Quantize	86
Set Velocity	86
Copy	86
Paste	86
Delete	86
Velocity Editor	87
Parameter Automation Editor	88
Play Sequence	89
1. Set host sync	89
2. Set tempo	89
3. Set loop	89
4. Set swing	89
5. Set metronome switch	90
6. Play	90
Record Sequence	90
1. Set recording mode	90
2. Play sequence	90
3. Record notes	90
4. Record parameters automation	90
5. Stop recording	90

Preset	91
File Menu	91
New...	91
Open...	91
Save	91
Preset Browser	92
Load Factory Preset	92
Load User Preset	92
Delete User Preset	92
Save User Preset	92
Backup/Restore User Presets stored in the device	92
Close File Browser	92
Setting Panel	93
General	93
Full Screen	93
Open User Guide	93
Open Host Setting	93
Version	93
MIDI Global	94
MIDI Thru	94
MIDI Monitor	94
Musical Typing	94
All Notes Off	94
Map MIDI CC	94
MIDI Synth1	95
OMNI	95
Input	95
Output	95
MIDI Local	95
MIDI Send	95

MIDI Receive	95
Min	95
Max	95
Stand Alone Setting	96
AbletonLink	96
Ableton Link	96
In-app notification	96
Sync Start/Stop	96
Connected Apps	96
Export Audio	97
Save As	97
Location	97
Length (Bars)	97
File Type	97
Sample Rate	97
Bit Depth	97
Export	97
Cancel	97
General	98
Run in Background	98
Resume Headphone Removed	98
Hardware Latency	98
Frame Size	98
MIDI	99
Input	99
Output	99
Bluetooth (BLE) MIDI	100
Central	100
Peripheral	100
Export Audio	101

Prepare for exporting audio	101
1. Stop playback	101
2. Select the first clip to play	101
3. Turn off metronome	101
Adjust export settings	101
1. Save As	101
2. Length	101
3. Location	101
4. File Type	101
5. Sample Rate	101
6. Bit Depth	101
Export Audio File	101
Map MIDI CC	102
Use External MIDI Keyboard with Stand Alone	103
Undo / Redo	104
macOS	105
Menu Bar	105
Application	105
File	105
Edit	106
View	106
Export	106
Window	107
Help	107
Preference	108
Enable Help Section	108
Disable State Recovery	108
Touch Bar (MacBook Pro)	109
1. Play / Stop	109
2. Tempo	109

Use Computer Keyboard as MIDI Keyboard	110
Keyboard Shortcut	111
AUv3 on Apple Garage Band (Mac)	112
Load Plug-in	112
Activate Plug-In	114
Offline Renering	114
Known Limitations	114
AUv3 on Apple Garage Band (iOS)	115
Load Plug-in	115
Change Plug-in Window Size	116
Record Notes	117
Edit Notes	117
Save Project	118
Host Sync	118
System Interruptions (iOS)	119
Specification	120
Release Notes	125
What's new in version 1.0	125

Introduction


Thank you for purchasing VAPolyFM. To help you get the most out of this product, please read this manual carefully.

VAPolyFM is a hybrid polyphonic synthesizer for iPhone, iPad and Mac. It features FM synthesizer and subtractive synthesizer. It operates as a stand alone or as an AudioUnit Extension (AUv3). Stand Alone supports Ableton Link, MIDI and audio file export.

FM synthesizer features 6 operators and 32 algorithm and it is inspired by FM synthesizers of the 1980's. Virtual analog subtractive synthesizer features two oscillators, resonant high pass filter, resonant low pass filter and two ADSR envelopes per voice. Built-in Effects include delay, chorus, flanger, reverb, eq and compressor. VAPolyFM also includes sequencer which features piano roll editor and parameter automation. Project files can be saved in iCloud Drive, so that the project can be accessed from iPhone, iPad or Mac.

Privacy Settings

VAPolyFM uses local area network to connect Ableton Link enable devices and it uses bluetooth to connect with bluetooth MIDI keyboard and controllers. When dialogue appears to confirm use of the local network or the bluetooth, tap OK to give a permission to use them. These settings can be edited in Privacy section of the Setting App.



Main Features

- FM Synthesizer. 6 operators and 32 algorithm.
- Virtual analog subtractive synthesizer.
- 8 voice polyphony.
- Built-in effects and sequencer.
- Support MIDI 2.0
- Support Audio Unit Extension (AUv3)
- Works on iPhone, iPad and Mac. Support iCloud Drive to share project files between the platforms.
- Audio Export. Linear PCM format (AIFF, WAV and CAF) and compressed format (AAC)
- Support Ableton Link, Bluetooth MIDI, MIDI In / Out.

System Requirements

- iOS 17.0 or later
- macOS 14.0 or later
- For iOS Devices, A13 Fusion or above is recommended.

AudioUnit Extension (AUv3) requires host application which support AudioUnit Extension. AudioUnit Extension is supported by Apple Logic and Apple Garage Band on iOS and macOS. For any other DAW, it depends on the application and some of them don't support AudioUnit Extension.

Use as Stand Alone

Stand Alone mode features Audio Export, Ableton Link, MIDI input / output and bluetooth MIDI. Sequencer can be synced with Ableton Link enabled devices and softwares.

Use as AudioUnit Extension (AUv3)

VAPolyFM supports AudioUnit Extensions. VAPolyFM works with host applications which support AUv3 plug-ins. By enabling host sync mode, VAPolyFM can be synced with tempo and transport state of the host application. VAPolyFM can send and receive MIDI message to/from the host, if the host supports midi in/out of AUv3.

Factory Preset

Factory presets contains only values of parameters of the synth and the effects. It doesn't contain any sequence data. When loading the preset, it will change the value of the parameters but sequence data remains the same.

User Preset

User Preset contains values of the synth parameters and the sequence data. When loading a user preset, value of the synth parameters and the sequence data are both changed.

User Presets can be saved in iCloud Drive or in AUv3 plug-in. User Presets in iCloud Drive can be accessed from iPhone, iPad or Mac. AUv3 Plug-In Preset is stored on the device and saved preset can be accessed from any host application which support AUv3 User Preset.

State Recovery

When VAPolyFM is used as a stand alone, it stores state of the app when the app is terminated. Stored data is recovered when it is launched at the next time. macOS version can disable this feature. The state is stored locally on the device.

About MIDI Latency

Sending or receiving MIDI notes and messages to Software Applications introduces a latency. If you have a problem of latency and DAW or host application has channel delay, adjust the delay time to compensate the latency.

- * Apple, Mac and GarageBand are trademarks of Apple Inc., registered in the U.S. and other countries.
- * Ableton and Link are trademarks of Ableton AG.
- * All products, companies and standard names are trademarks or registered trademarks of their respective holders.


User Interface



macOS



Tool Bar



- 1. Host Sync
Tap this button to enable / disable host sync. When host sync is enabled, tempo and transport is controlled by the host application.
- 2. Play/Stop
Tap this button to play / stop the sequencer.
- 3. Record
Tap this button to enable / disable recording mode.
- 4. Metronome
Tap this button to enable / disable metronome.
- 5. Swing
Tap this button to show Swing menu.



- 6. Beat Counter
Indicates current beat time as a format of bar, beat, and sixteenth.
- 7. Time Signature
Tap this button to show Time Signature menu.



- 8. Tempo
Adjust BPM (Beat Per Minutes).
- 9. Undo
- 10. Redo
Tap the button to undo / redo.
- 11. Setting Panel
Tap this button to open setting panel.



2. Preset



Indicates name of the selected preset. Tap this button to show preset browser.

3. Parameter

Indicates name and value of the selected parameter. Use plus button, minus button and slider to adjust the value. Double tap to enable menu and tap on the name to show parameter list.

4. Synth

Tap this button to show synth menu.




7. Visualizer

Tap this button to show audio visualization tool. Hold this button (right click on macOS) to show visualizer menu.



8. Sequencer

Tap this button to show sequencer. Hold this button (right click on macOS) to show sequencer menu.



* Content of the menu is dependent on the platform.

5. Bottom Module


Tap this button to show VA Synth, Effects or Global module in bottom section.

6. Keyboard

Tap this button to show keyboard. Hold this button (right click on macOS) to show keyboard menu.

FM Synth

Global



1. Algorithm

Select an algorithm.

2. Feedback

Adjust amount of feedback.

3. OSC Key Sync

Turn OSC Key Sync on or off.


4. Transpose

Adjust amount of Transpose in semi tones.

5. Master Tune

Adjust amount of master tune in cents.

Operator



1. Power Switch

Turn operator on or off.

2. Coarse

Adjust amount of coarse tuning.

3. Level 2

Adjust amount of output level.

4. Level 3

Select ratio mode or fixed mode.

5. Level 4

Adjust amount of fine tuning.

6. Level 5

Adjust amount of detune in cents.



1. Tab Selector

Select a tab.

2. Envelope stage time

Adjust time of the stage.

3. Envelope stage level

Adjust level of the stage.

4A. Key Follow

Adjust amount of key follow.

4B. EG Velocity

Adjust amount of key velocity to affect level of envelope.

4C. AM Depth

Adjust amount of amplitude modulation.

4D. PM Depth

Adjust amount of pitch modulation.

5A. Break Point

Adjust key tracking break point.

5B. Left Depth

Adjust depth of left section.

5C. Left Curve


Select curve of left section.

5D. Right Depth

Adjust depth of right section.

5E. Right Curve

Select curve of right section.



1. Tab Selector

Select a tab.

2. Pitch Envelope stage time

Adjust time of the stage.

3. Pitch Envelope stage level

Adjust level of the stage.

4A. LFO Speed

Adjust frequency of LFO.

4B. LFO Key Sync

Turn Key Sync on or off.

4C. LFO Wave

Select wave shape of LFO.

4D. LFO Delay

Adjust amount of trigger delay.

4E. LFO PMD

Adjust amount of pitch modulation.

4F. LFO AMD

Adjust amount of amplitude modulation.

5A. PB Range & Step

Adjust pitch bend range and step.

5B. MW Range & Assign


Adjust mod wheel range and assign.

5C. AT Range & Assign

Adjust aftertouch range and assign.

VA Synth and Effects

Oscillator 1



1. OSC1 Tab

Tap to Select OSC1 Tab.

2. Mod Tab

Tap to select Mod Tab.

3. Mod+ Tab

Tap to select Mod+ Tab.

4. Level Meter

Indicate output level of oscillator 1.

5. Tune

Adjust pitch of the oscillator (+/- 24 semitones).

6. Shape

Adjust shape of the oscillator waveform.

8. OSC Sync

Turn on/off oscillator sync.

9. PW

Adjust amount of the pulse width.

11. FM LFO Int

Adjust intensity of the LFO frequency modulation.

12. Shape LFO Int

Adjust intensity of the LFO shape modulation.

13. PW LFO Int

Adjust intensity of the LFO pulse width modulation.

14. FM Mode

Select frequency modulation mode.

15. LFO Source

Select source of LFO modulation.

17. FM Env Int

Adjust intensity of the envelope frequency modulation.

18. Shape Env Int

Adjust intensity of the envelope shape modulation.

19. PW Env Int

Adjust intensity of the envelope pulse width modulation.

20. FM XMOD Int

Adjust intensity of the XMOD frequency modulation.


21. Shape XMOD Int

Adjust intensity of the XMOD shape modulation.

22. Env Source

Select an source of the envelope modulation.

Oscillator 2 and LFO1



1. OSC2 Tab

Tap to Select OSC2 Tab.

2. Mod Tab

Tap to select Mod Tab.

3. LFO1 Tab

Tap to select Arp Tab.

4. Level Meter

Indicate output level of oscillator 2.

5. Tune

Adjust pitch of the oscillator (+/- 24 semitones).

6. Tune Fine

Adjust pitch of the oscillator (+/- 50 cents).

7. Shape

Adjust shape of the oscillator waveform.

8. KBD SW

Turn on/off keyboard switch.

9. LFO SW

Turn on/off low frequency switch.

10. PW

Adjust amount of the pulse width.

11. FM LFO Int

Adjust intensity of the LFO frequency modulation.

12. Shape LFO Int

Adjust intensity of the LFO shape modulation.

13. PW LFO Int

Adjust intensity of the LFO pulse width modulation.

14. FM Mode

Select frequency modulation mode.

15. LFO Source

Select source of LFO modulation.

17. LFO Tune

Adjust pitch of the low frequency oscillator.

18. LFO Shape

Select shape of the low frequency oscillator waveform.

20. LFO Sync

Turn on/off tempo sync switch.


21. Key Trigger

Turn on/off Key Trigger switch.

22. LFO AM

Select envelope amplitude modulation source.

Mixer, Effect Send and LFO2



1. Mixer Tab

Tap to Select Mixer Tab.

2. EFX Tab

Tap to select LFO Tab.

3. LFO2 Tab

Tap to select EFXTab.

4. Level Meter

Indicate output level of the mixer.

5. FM Level

Adjust level of FM.

6. OSC1 Level

Adjust level of the OSC1.

7. OSC2 Level

Adjust level of the OSC2.

8. Noise Level

Adjust level of pink noise and white noise.

9. Sub Level

Adjust level of the sub oscillator.

10. Ring Level

Adjust level of the ring modulator.

11. Delay Send

Adjust aux1 (delay) send level.

12. C/F Send

Adjust aux2 (chorus / flanger) send level.

13. Reverb Send

Adjust aux3 (reverb) send level.

14. Delay Pre / Post

Select source signal for Delay.

15. C/F Pre / Post

Select source signal for Chorus / Flanger.

16. Reverb Pre / Post

Select source signal for Reverb.

17. LFO Tune

Adjust pitch of the low frequency oscillator.

18. LFO Shape

Select shape of the low frequency oscillator waveform.

20. LFO Sync

Turn on/off tempo sync switch.

21. LFO Key Trigger


Turn on/off Key Trigger switch.

22. LFO AM

Select envelope amplitude modulation source.

“Pre” means pre fader. Signal is taken before volume level is applied to the signal.
“Post” means post fader. Signal is taken after volume level is applied to the signal.

LPF, HPF and Env1



1. LPF Tab

Tap to Select LPF Tab.

2. HPF Tab

Tap to select HPF Tab.

3. Env1 Tab

Tap to select Env1 Tab.

4. Level Meter

Indicate output level of the filter.

5. LPF Cutoff

Adjust cutoff of the low pass filter.

6. Env Mod Int

Adjust intensity of the envelope modulation.

7. LFO Mod Int

Adjust intensity of the LFO modulation.

8. LPF Resonance

Adjust resonance of the low pass filter.

9. Key Follow

Adjust amount of the key follow.

10. VCF Slope

Select a filter slope when cascaded OTA filter model is selected. Options are -12dB/Octave and -24dB/Octave.

11. HPF Cutoff

Adjust cutoff of the high pass filter.

12. Env Mod Int

Adjust intensity of the envelope modulation.

13. LFO Mod Int

Adjust intensity of the LFO modulation.

14. HPF Resonance

Adjust resonance of the high pass filter.

17. Env Attack

Adjust attack time of the envelope.

18. Env Decay

Adjust decay time of the envelope.

19. Env Delay

Adjust delay time to trigger envelope.

20. Env Sustain

Adjust sustain level of the envelope.


21. Env Release

Adjust release time of the envelope.

22. Env KeyFollow

Adjust amount of the key follow.

AMP, FM AMP and Env2



1. AMP Tab

Tap to Select Amp Tab.

2. FM AMP Tab

Tap to select VCA Tab.

3. Env2 Tab

Tap to select Env2 Tab.

4. Level Meter

Indicate output level of the synth.

5. Volume

Adjust volume of the amplifier.

6. Pan Int

Adjust intensity of the pan modulation.

7. AM Int

Adjust intensity of the amplitude modulation.

8. Env Source

Select a volume envelope.

9. Pan LFO Source

Select source of pan modulation.

10. AM LFO Source

Select source of amplitude modulation.

11. Volume

Adjust volume of the amplifier.

12. Pan Int

Adjust intensity of the pan modulation.

13. Pan LFO Source

Select source of pan modulation.

14. Delay Send

Adjust aux1 (delay) send level.

15. C/F Send

Adjust aux2 (chorus / flanger) send level.

16. Reverb Send

Adjust aux3 (reverb) send level.

17. Env Attack

Adjust attack time of the envelope.

18. Env Decay

Adjust decay time of the envelope.

19. Env Delay

Adjust delay time to trigger the envelope.

20. Env Sustain

Adjust sustain level of the envelope.


21. Env Release

Adjust release time of the envelope.

22. Env Key Follow

Adjust amount of the key follow.

Global, ARP and VCF



1. Global Tab

Tap to Select OSC2 Tab.

2. ARP Tab

Tap to select Mod Tab.

3. VCF Tab

Tap to select VCF Tab.

4. Level Meter

Indicate output level of oscillator 2.

5. Env1 Velocity

Turn velocity option on or off.

6. Env2 Velocity

Turn velocity option on or off.

7. Stereo

Adjust amount of stereo spread.

8. Unison

Turn unison option on or off.

9. Voices

Select number of voices for unison.

10. Glide Time

Adjust time of the Glide.

11. Arp Rate

Adjust frequency of Arp clock

12. Pattern

Select a pattern of Arp.

14. Sync

Turn tempo sync on or off.

15. Arp Switch

Turn Arp on or off.

17. LP Env Source

Select an envelop for frequency modulation. waveform.

18. LPF LFO Source

Select source of LFO modulation.

20. HP Env Source

Select an envelop for frequency modulation.

21. HPF LFO Source

Select source of LFO modulation.

KBD Control Routing

Sources	Controller Routing					
Mod Wheel	OSC1 FM LFO	OSC1 SH LFO	OSC1 PW LFO	OSC1 FM Env	OSC1 SH Env	OSC1 PW Env
Velocity	CSC1 FM XM	OSC1 SH XM	OSC2 FM LFO	OSC2 SH LFO	OSC2 PW LFO	LPF CF
Aftertouch						
Poly Pressure	HPF CF	Amp Vol	Amp Pan	FM PM	FM AM	FM EGBias


1. Control Sources

Select Keyboard Controller.

2. Control Targets

Select target parameters to control.

DLY (Delay)



1. Main Tab

Tap to Select Main Tab.

2. Sync Switch

Tap to enable / disable tempo sync.

3. Level Meter

Indicate output level of the delay.

4. Delay Time

Adjust delay time.

5. LFO Frequency

Adjust frequency of LFO (low frequency oscillator).

6. HP Frequency

Adjust frequency of high pass filter for the delayed sound.

7. Feedback

Adjust amount of the feedback.

8. LFO Int

Adjust amount of LFO delay time modulation.


9. LP Frequency

Adjust frequency of low pass filter for the delayed sound.

10. Delay Time (sync)

Adjust delay time which is synced to the current tempo.

C/F (Chorus / Flanger)



1. Main Tab

Tap to Select Main Tab.

2. Sub Tab

Tap to select Sub Tab.

3. Sync Switch

Tap to enable / disable tempo sync.

4. Level Meter

Indicate output level of the chorus / flanger.

5. LFO Freq

Adjust frequency of the LFO.

6. LFO Int

Adjust amount of LFO delay time modulation.

7. Delay Time

Adjust delay time.

8. Chorus/Flanger

Select Chorus or Flanger.

9. Feedback

Adjust amount of the feedback.

10. Stereo Width

Adjust stereo width.

11. Sine/Triangle

Adjust shape of the LFO waveform.

12. HP Freq

Adjust frequency of high pass filter for the effected sound.


13. LP Frequency

Adjust frequency of high pass filter for the effected sound.

14. LFO Frequency (sync)

Adjust LFO frequency which is synced to the current tempo.

REV (Reverb)



1. Main Tab

Tap to Select Main Tab.

2. Sub Tab

Tap to select Sub Tab.

3. Sync Switch

Tap to enable / disable tempo sync.

4. Level Meter

Indicate output level of the reverb.

5. Size

Adjust room size of the late reflection.

6. Decay

Adjust decay of the late reflection.

7. Damp

Adjust absorption of high frequency in the late reflection.

8. Auto Size

Select to enable / disable auto size mode.

9. Pre Delay

Adjust pre delay time of the early reflection.

10. LP Frequency

Adjust frequency of output low pass filter.

11. LFO Frequency

Adjust frequency of LFO (low Frequency oscillator).

12. HP Frequency

Adjust frequency of input high pass filter.

13. Early/Late

Adjust amount of the early reflection and amount of the late reflection.

14. LFO Int

Adjust amount of LFO delay time modulation.

15. LP Frequency

Adjust frequency of input low pass filter.

16. EFX Input

Adjust amount of input signal from delay and chorus.


17. Size (sync)

Adjust room size which is synced to the current tempo.

18. LFO Frequency (sync)

Adjust LFO frequency which is synced to the current tempo.

EQ (3 Band EQ / Effect Mixer)



1. Main Tab

Tap to Select Main Tab.

2. EFX Tab

Tap to select EFX Tab.

3. Level Meter

Indicate output level of the EQ.

4. High Frequency

Adjust frequency of high shelving filter.

5. Mid Frequency

Adjust frequency of mid peak / notch filter.

6. Low Frequency

Adjust frequency of low shelving filter.

7. High Gain

Adjust gain of the high shelving filter.

8. Mid Gain

Adjust gain of the mid peak / notch filter.

9. Low Gain

Adjust gain of the low shelving filter.

10. Delay Level

Adjust level of delay.

11. C/F Level

Adjust level of chorus / flanger.

12. Reverb Level

Adjust level of reverb.

13. Delay Bypass

Turn on/off bypass delay effect.


14. C/F Bypass

Turn on/off bypass chorus / flanger effect.

15. Reverb Bypass

Turn on/off bypass reverb effect.

CMP (Compressor)



1. Main Tab

Tap to Select Main Tab.

2. Sub Tab

Tap to select Sub Tab.

3. Master Tab

Tap to select Aux Tab.

4. Level Meter

Indicate level of the master output.

5. Reduction Gain Meter

Indicate amount of gain reduction.

6. Attack

Adjust time to start compression.

7. Threshold

Adjust level of threshold to begin compression.

8. Release

Adjust time to end compression.

9. Makeup

Adjust amount of makeup gain.

10. Input Gain

Adjust amount of input gain.

11. HP Frequency

Adjust frequency of high pass filter at the input of the compressor.

12. Ratio

Adjust compression ratio.

13. Dry/Wet

Adjust amount of the dry and wet signal.

14. Volume

Adjust master volume.


15. Pan

Adjust master pan.

16. Mute

Turn on/off mute.

Keyboard



1. Pitch Wheel

Adjust pitch of the oscillators. Range is plus / minus one octave.

2. Modulation Wheel

Adjust amount of the modulation.

3. Split Button

Tap this button to split keyboard.

4. Key Range

Use plus / minus buttons to adjust range of the keyboard. Indicator shows lowest note of the keyboard¹. When “Midi Monitor” is enabled, the range is automatically set based on the incoming midi note.

5. Velocity

Use plus/minus button to adjust keyboard velocity.

6. Hold


Tap this button to enable /disable key holding.

7. Scroll

Tap this button to enable/disable keyboard scrolling.

¹ Middle C (midi note 60) is C3.

Visualizer



1. Audio Source Selector

Tap this button to show a list. Select audio source for the visualization.

2. Audio Source Selector

Tap this button to show a list. Select audio source for the visualization.

3. Oscilloscope Button

Tap this button to select Oscilloscope.


4. Spectrum Plot Button

Tap this button to select Spectrum Plot.

5. Spectrogram Button

Tap this button to select Spectrogram.



Tap and hold (right click on macOS) to show context menu.



Select a tool for audio visualization. Options are Oscilloscope, Spectrum Plot and Spectrogram.


Select a source of audio for the visualization.

Sequencer



Clip contains note events and parameter automation events for each timbral. Maximum length of clip is 16 bars. Maximum number of clips are 8.

Clip Editor



1. Launch Button

Tap this button to play/stop clip.

2. Edit Button

Tap this button to open piano roll editor.


3. Loop Selector

Select loop options.

4. Add Button

Tap this button to add edit button.

Piano Roll Editor



1. Loop Menu

Press and hold (right click on macOS) Time Range Selector to show this menu. Tap on “Set Loop Length” to set loop length to current length selected by the Time Range Selector.

2. Scale Menu

Press and hold (right click on macOS) editor to show this menu.

3. Editing Menu

Press and hold (right click on macOS) note to show this menu.

4. Time Range Selector

Select time range for editing and for loop length. On iOS, pinch gesture control zooming and drag gesture control scroll position.

5. Note Range Selector

Select note range for editing. On iOS, pinch gesture control zooming and drag gesture control scroll position.

6. Loop Range

Tap this button to show Loop Menu.



7. Scale

Tap this button to show Scale Menu

8. Parameter Automation Button

Tap this button to show Parameter Automation Editor

Parameter Automation Editor



1. Loop Menu

Press and hold (right click on macOS) Time Range Selector to show this menu. Tap on “Set Loop Length” to set loop length to current length selected by the Time Range Selector.

2. List Menu

Press and hold (right click on macOS) item in parameter list to show this menu.

3. Editing Menu

Press and hold (right click on macOS) editor to show this menu.

4. Time Range Selector

Select time range for editing and for loop length.

5. Add Button

Tap this button to select parameter to edit.


6. Piano Roll Button

Tap this button to show piano roll editor.


Synthesizer

VAPolyFM features 8 voice polyphonic FM synthesizer and VA synthesizer. Output of FM synthesizer can be routed to mixer of VA synthesizer and main output.

Block diagram



Control Signal & MIDI Flow




FM Synthesizer

FM synthesis generate rich harmonic tone by modulating carrier by modulator. Carrier and modulator are called operator. Operator contains sine wave oscillator, amplifier and envelope generator. Routing of operators is defined by algorithm.




Block diagram FM Synthesizer



Operator

Operator is a basic building block of FM synthesizer. Operator contains sine wave oscillator, amplifier and envelope generator. Operator can be carrier or modulator based on the selected algorithm.



Power Switch

Tap on operator title to turn it on or off.

Coarse

Set coarse frequency of oscillator. When ratio mode is selected, it set integer value of harmonic index ratio from 0.5 to 31. When fixed mode is selected, it set fixed frequency of 1 Hz, 10Hz, 100Hz or 1KHz.

Level

Adjust output level of operator in dB scale from -60 dB to 0 dB.

Mode

Select ratio mode or fixed mode. In ratio mode, frequency of oscillator can be set as harmonic index ratio. In fixed mode, frequency of the oscillator can be set as fixed frequency (Hz).

Fine

Set fine frequency of oscillator. When mode is ratio, range is from 1 to 1.99 times. When mode is fixed, range is from 1 to 9.772 times. (frequency = coarse x fine.)

Detune

Adjust pitch of the oscillator. (+/- 7 cents)



EG T1...T4

Adjust time of stage 1...4.

EG L1...L4

Adjust level of stage 1...4 in dB scale from -60 dB to 0 dB.

Key Follow

Adjust amount of key follow. Time is reduced when pitch is increased.

EG Velocity

Adjust amount of velocity to affect level of envelope.

AM Depth

Adjust master amount of amplitude modulation.

PM Depth

Adjust master amount of pitch modulation.

Key Tracking Break Point

Adjust break point as note value.

Key Tracking Left Depth

Adjust amount of key tracking for the selected curve.

Key Tracking Left Curve

Select curve from -linear, +linear, -Exponent or +Exponent.


Key Tracking Right Depth

Adjust amount of key tracking for the selected curve.


Key Tracking Right Curve

Select curve from -linear, +linear, -Exponent or +Exponent.

Five Stage Envelope Generator



Key Tracking



Global



Algorithm

Select an Algorithm. Algorithm defines routing of operators, such as which operators are carrier and which operators are modulators.

Feedback

Adjust amount of feedback. Which operator to receive feedback is defined by algorithms.

OSC Key Sync


Turn OSC key Sync on or off. When it is turned on, oscillator reset each time key is pressed.

Transpose

Adjust amount of transpose (+/- 24 semi tones).

Master Tune

Adjust amount of master tune (+/- 75 cents).



Pitch EG T1...T4

Adjust time of stage 1...4.

Pitch EG L1...L4

Adjust level of stage 1...4 in dB scale from -60 dB to 0 dB.

LFO Speed

Adjust frequency of LFO. Range is from 0.04Hz to 41.2Hz.

LFO Key Sync

Turn Key Sync on or off. When it is turned on, LFO reset each time key is pressed.

LFO Wave

Select wave shape of LFO. Options are triangle, saw down, saw up, square, sine and s/hold (random).

LFO Delay

Adjust amount of delay to start of LFO when key is pressed.

LFO PMD

Adjust amount of pitch modulation. PM depth of operator need to be greater than zero in order to apply pitch modulation to the operator.

LFO AMD

Adjust amount of amplitude modulation. AM depth of operator need to be greater than zero in order to apply amplitude modulation to the operator.

PB Range

Adjust range of pitch bend from 0 to +/- 1 octave.

PB Step

Adjust step of pitch bend from 0 to 12. Length of step is step value multiplied by 100 cents.

MW Range

Adjust range of mod wheel from 0% to 100%.

MW Assign

Select targets of mod wheel. Targets are pitch, amplitude and EG bias.

AT Range

Adjust range of aftertouch from 0% to 100%.


AT Assign

Select targets of aftertouch. Targets are pitch, amplitude and EG bias.

VA Synthesizer



Block diagram VA Synthesizer



Oscillator 1

Oscillator 1 generates continuously variable wave shape, from triangle wave to saw wave and from the saw wave to square wave. Pulse width can be adjusted for triangle and square wave. Oscillator 1 also generate sub, which is a square wave and its frequency is one octave below of the main pitch. Oscillator 1 can be synchronized to oscillator 2. Total amount of modulation to the oscillator can be control by mod int, mod wheel, after touch or poly aftertouch. Pitch bend can be used to shift frequency of the oscillator +/- one octave.



Tune

Adjust pitch of the oscillator. (maximum +/- 24 semitones)

Shape

Adjust shape of the waveform. Fully counter clockwise position is Triangle, center is Saw, and fully clockwise position is Square.

Sync

Turn this switch on to sync OSC1 to OSC2. (OSC2 are master.)

It forces OSC1 to follow frequency of the OSC2 in “hard” synchronization. Adjusting Tune of OSC1 produces unusual wave shapes resulting unusual timber. Typical use of Sync is modulate frequency of OSC1 by envelope. It will produce classic Sync Sound.

When OSC1 waveform is Square and Tune of OSC1 is lower than OSC2, it produces DC signal resulting no audible output.

PW (Pulse Width)

Adjust pulse width of the triangle wave and the square wave.

When Square wave is selected, pulse width of 0% and 100% produce DC signal² resulting no audible output.

² DC Signal is always positive or always negative and produce no sound.

Oscillator 2

Oscillator 2 generate continuously variable wave shape, from triangle wave to saw wave and from the saw wave to square wave. Pulse width can be adjusted for square wave. Oscillator 2 can be used for modulation source. When KBD switch is off, keyboard is disconnected from the oscillator 2, and the pitch of the oscillator 2 can be controlled by tune dial. When Low switch is on, the oscillator 2 can be used as LFO³. Total amount of modulation to the oscillators can be control by mod int, mod wheel aftertouch or poly aftertouch. Pitch bend can be used to shift frequency of the oscillator +/- one octave.



Tune

Adjust pitch of the oscillator (+/- 24 semitones). When KBD switch is turned off, the pitch can be adjusted by MIDI note value. When KBD switch is turned off and Low switch is turned on, the frequency can be adjusted from 0.04Hz to 42.2Hz.

Fine (Fine Tune)

Adjust pitch of the oscillator. (+/- 50 cents)
Use Fine Tune to detuning OSC2 relative to OSC1.

Shape

Adjust shape of the waveform. Fully counter clockwise position is Triangle, center is Saw, and fully clockwise position is Square.

KBD (Keyboard) SW

Turn this switch on to control pitch of the oscillator by keyboard. When this switch is turned off, OSC2 is disconnected from keyboard and pitch of the oscillator can be adjusted by Tune dial. This is useful to modulate frequency or shape of the OSC1 by XMOD⁴ in audio range.

LFO SW

When this switch is turned on, OSC2 can be used as a LFO. (from 0.04Hz to 42.2Hz). This is useful to modulate frequency or shape of the OSC1 by XMOD in low frequency range.

PW (Pulse Width)

Adjust pulse width of the square wave. Pulse width of 0% and 100% produce DC signal resulting no audible output.

³ Low Frequency Oscillator

⁴ Cross Modulation

Oscillator Modulation

Amount of modulation to frequency, shape and pulse width of the oscillators can be adjusted in modulation section. There are three sources, envelope, LFO and XMOD. Targets of envelope are frequency, shape and pulse width of the oscillator 1. Targets of LFO are frequency and shape, and pulse width of the oscillator 1 and 2. Targets of XMOD are frequency and shape of the oscillator 1. There are two mode for frequency modulation. The frequency is modulated by volts per octave basis (+/- 4 octaves) in exponential mode and the frequency is modulated by hertz per volt basis (+/- 2.25 octaves) in linear mode.

LFO Modulation



FM LFO (LFO to Frequency)

Adjust amount that LFO modulates frequency of the oscillator.

Shape LFO (LFO to Shape)

Adjust amount that LFO modulates shape the oscillator.

PW LFO (LFO to Pulse Width)

Adjust amount that LFO modulates pulse width of the oscillator.

Frequency Modulation Type

Select frequency modulation type, linear or exponential. The frequency is modulated by volts per octave basis (+/- 4 octaves) in exponential mode and the frequency is modulated by hertz per volt basis (+/- 2.25 octaves) in linear mode.

LFO Source

Select source of LFO modulation.

Envelope & Cross Modulation



FM Env (Envelope to Frequency)

Adjust amount that envelope modulates frequency of the oscillator.

Shape Env (Envelope to Shape)

Adjust amount that envelope modulates shape of the oscillator.

PW Env (Envelope to Pulse Width)

Adjust amount that envelope modulates pulse width of the oscillator.

FM XMOD (XMOD to Frequency)

Adjust amount that oscillator 2 modulates frequency of the oscillator.

Shape XMOD (XMOD to Shape)

Adjust amount that oscillator 2 modulates shape of the oscillator.

Env Source

Select an envelope for the envelope modulation.

Mixer

Level of FM Synthesizer, oscillator 1, oscillator 2, sub, ring and noise can be adjusted in the mixer section. Ring is output of ring modulator, which ring modulate output of the oscillator 1 and output of the oscillator 2. Noise is output of the noise generator.



FM

Adjust level of FM Synthesizer output.

OSC1, OSC2

Adjust level of the oscillator output.

Sub (Sub Oscillator Level)

Adjust level of the sub waveform. The sub is a square wave and generated by Oscillator 1. It is one octave lower than the waveform of the Oscillator 1.

Ring (Ring Modulation Level)

Adjust level of the ring modulator. (The output is ring modulation of OSC 1 and OSC 2)

Ring Modulator produces signal which contains sums and differences of the two oscillator frequency. Adjust frequency of the oscillators to experiment with the sounds. Ring Modulator tends to produce metallic or percussive sounds such as bell, chimes or gongs.

Noise (Noise Level)

Adjust level of the noise. Turn the dial to counter clockwise to increase level of pink noise. Turn the dial to clockwise to increase level of white noise.

Low Pass Filter

This low pass filter is modeled on the Sallen-Key -12dB per octave low pass filter circuit. The filter is capable of self oscillation when resonance is at the maximum position. Cutoff frequency of the low pass filter can be modulated by an ADSR envelope and a LFO. Also the cutoff frequency can be controlled by keyboard with the amount adjusted by key follow parameter.



Cutoff

Adjusts the cutoff frequency of the low pass filter.

Resonance

Adjusts amount of the resonance of the low pass filter.

Env Mod (Envelope Modulation Intensity)

Adjusts amount that the filter envelope modulates the cutoff frequency of the low pass filter.

LFO Mod (LFO Modulation Intensity)

Adjusts amount that the LFO modulates the cutoff frequency of the low pass filter.

Key Follow

Adjust amount that the keyboard controls the cutoff frequency of the low pass filter.

VCF Slope

Select -12dB/Octave or -24 dB/Octave.

High Pass filter

This high pass filter is modeled on The Sallen-Key -12dB per octave high pass filter circuit. The filter is capable of self oscillation when resonance is at the maximum position. Cutoff frequency of the high pass filter can be modulated by an ADSR envelope and a LFO. Also the cutoff frequency can be controlled by keyboard with the amount adjusted by key follow parameter.



Cutoff

Adjusts the cutoff frequency of the high pass filter.

Resonance

Adjusts amount of the resonance of the high pass filter.

Env Mod Int (Envelope Modulation Intensity)

Adjusts amount that the filter envelope modulates the cutoff frequency of the high pass filter.


LFO Mod Int (LFO Modulation Intensity)

Adjusts amount that the LFO modulates the cutoff frequency of the high pass filter.

Key Follow

Adjust amount that the keyboard controls the cutoff frequency of the high pass filter.

VCF Setting



LP Env Source

Select envelope to modulate the cutoff frequency.

LP LFO Source

Select source of LFO modulation.

HP Env Source

Select envelope to modulate the cutoff frequency.

HP LFO Source

Select source of LFO modulation.

AMP (Amplifier)

The output signal of the filter is routed to the amplifier. The signal is shaped by gate signal or ADSR envelope. The audio signal can be modulated by LFO. The output level can be adjusted by volume parameter.



Volume

Adjust volume of the output signal.

LFO PAN (Pan Modulation Intensity)

Adjust amount that LFO modulates amount of the pan of the output signal.

LFO AM (Amplitude Modulation Intensity)

Adjust amount that LFO modulates amplitude of the output signal.

Gate/Env(ADSR)

Select a volume envelope for the amplifier. The envelope can be chosen from gate or ADSR envelope.

Pan Source


Select source of Pan modulation. Select manual to adjust pan manually.

AM Source

Select source of Amplitude modulation.

ADSR (Envelope Generator)

ADSR is an analog style non-linear envelope generator. When velocity switch is on, amplitude of the envelope is controlled by MIDI velocity.



Attack

Adjust the attack time of the ADSR envelope (from 1 ms to 6 sec)

Release

Adjust release time of the ADSR envelope (from 1 ms to 10 sec)

Decay

Adjust the decay time of the ADSR envelope (from 1 ms to 10 sec)

Delay


Adjust delay time to trigger the ADSR envelope (from 0 ms to 10 sec)

Sustain

Adjust sustain amount of the ADSR envelope (from 0% to 100%)


Key Follow

Adjust amount that CV affect length of envelope.



LFO

LFO (Low Frequency Oscillator) can generate 6 wave shapes and the frequency of the LFO can be set by Hz or note value when LFO is synchronized to tempo. Amplitude of the LFO can be modulated by ADSR envelope.



Tune

Adjust frequency of the LFO. When sync is off, range of the frequency is from 0.04Hz to 42.2Hz. When sync is on, range of the rate is from 1/64 to 8 bars.

Shape

Select shape of the LFO waveform. Wave shapes are sine, saw, down saw, square, triangle and random.

Sync

Turn this switch on to sync the rate of the LFO with tempo.

Key Trg (Key Re-Trigger)

Turn this switch on to restart the LFO cycle every time a new note is played.

AM Env

Select an envelope to modulate amplitude of LFO.

Effect Send

Adjust send level and pre / post options for signal routed to delay, chorus/flanger and reverb effects.



Delay Send

Adjust level of the signal send to delay effect.

Delay Pre/Post

Select Pre (pre fader) or post (post fader) to specify source of the signal for delay.

C/F Send

Adjust level of the signal send to chorus / flanger effect.

C/F Pre/Post

Select Pre (pre fader) or post (post fader) to specify source of the signal for chorus/flanger.

Reverb Send

Adjust level of the signal send to reverb effect.

Reverb Pre/Post

Select Pre (pre fader) or post (post fader) to specify source of the signal for reverb.

Effect Output Mixer

Output Signals from the effects can be adjusted by effect mixer.



Delay Level

Adjust level of delay signal to EQ.

Delay Bypass

Turn off to bypass delay.

C/F Level

Adjust level of Chorus / Flanger signal to EQ.

C/F Bypass

Turn off to bypass Chorus / Flanger.

Reverb Level


Adjust level of Reverb Signal to EQ.

Reverb Bypass

Turn off to bypass Reverb.

ARP (Arpeggio)

Adjust parameters for Arpeggio.



Arp Rate

Adjust frequency of the clock for arpeggio. When tempo sync is off, range of the frequency is from 1 Hz to 20 Hz. When tempo sync is on, range of the rate is from 1/32 to 1 bars.

Arp Pattern

Select a pattern of the arpeggio. Options are up, down, up & down and random.

Arp Switch


Turn this switch on to enable arpeggio.

Arp Sync

Turn this switch on to sync the rate of the clock with tempo.

Global

Adjust parameters for global options



Env1 & Env2 KBD Velocity

When velocity switch is turned on, amplitude of the envelope is controlled by MIDI velocity. When velocity is turned off, amplitude of envelope is set to maximum value. (midi velocity 127)

Stereo

Adjust amount of pan for each voices.

Unison

Turn this switch on to enable unison mode. Unison mode make 8 voices to be used for a single note.

Voices


Select number of voices for unison.

Glide Time

Adjust time of the glide from 10 ms to 10 second. Glide is applied in polyphonic and unison when notes are played in legato.

Master Output

Level and Pan of the master output can be adjusted in master tab of compressor.



Volume

Adjust level of the master output.

Pan

Adjust pan of the master output.

Mute

Turn on to mute master output.

KBD Control Routing


Select targets for Keyboard Controllers.

Sources	Controller Routing					
Mod Wheel	OSC1 FM LFO	OSC1 SH LFO	OSC1 PW LFO	OSC1 FM Env	OSC1 SH Env	OSC1 PW Env
Velocity	OSC1 FM XM	OSC1 SH XM	OSC2 FM LFO	OSC2 SH LFO	OSC2 PW LFO	LPF CF
Aftertouch						
Poly Pressure	HPF CF	Amp Vol	Amp Pan	FM PM	FM AM	FM EGBias

Effects

Delay

Signal Flow



Delay Time

Adjust delay time from 20 ms to 1200 ms. When sync switch is turned on, delay time can be set as note value which is synchronized to the tempo. Valid range of the note value is automatically adjusted base on the current tempo.

Regeneration

Adjust feedback from 0 % to 100 %. You can change sound of the feedback by adjusting frequency of the high-pass filter and the low-pass filter.

Modulation


Modulation can be applied to the delayed signal. LFO (Low Frequency Oscillator) generates sine wave for the modulation.

Adjust LFO frequency from 0.01 Hz to 10 Hz.

Adjust LFO Intensity from 0 to 1.0, which adjust modulation width from 0 ms to +/- 10 ms.

Chorus / Flanger

Signal Flow



Input Signal Level

Level of input signal should be about -6dB or less. If the input signal is too hot, it will cause distortion in output signal.

Effect Type

Select effect type from chorus or flanger. Ranges of the delay time and the LFO Intensity change based on the selected effect type.

Modulation Speed

LFO Frequency dial controls speed of the modulation. When sync switch is turned on, LFO Frequency can be set as note value which is synchronized to the tempo. Valid range of the note value is automatically adjusted base on the current tempo.

Modulation Width

LFO Intensity dial controls width of the modulation and delay time dial controls center position of the modulation.

When chorus effect is selected, range of the LFO intensity is from 0 ms to 1 ms and range of the delay time is from 1 ms to 40 ms.

When flanger effect is selected, range of the LFO intensity is from 0 ms to 12 ms and range of the delay time is from 1 ms to 13 ms.

Rotate delay time dial counterclockwise to emphasize higher frequency or clockwise to emphasize lower frequency.⁵

LFO Shape

LFO shape dial controls shape of the LFO waveform. When the dial is rotated fully counterclockwise, shape of the waveform is sine wave. When the dial is rotated fully clockwise, shape of the waveform is triangle wave.

Stereo Width

Stereo Width dial controls phase offset of the LFO. When the dial is rotated fully counterclockwise, stereo width is 0%. (phase offset is 0 degree) When the dial is rotated fully clockwise, stereo width is 100%. (phase offset is 180 degree)

Regeneration

Feedback dial controls amount of regeneration from 0 % to 100 %. Turning the feedback dial clockwise enhances amount of the feedback effect.


⁵ If compared with manual knob of the analog flanger guitar pedal, emphasized frequency moves reverse direction.

Filters

Delayed signal is routed to high-pass filter and low-pass filter before mixed with dry signal. HP frequency controls frequency of the high-pass filter. LP frequency controls frequency of the low-pass filter.

Reverb

Signal Flow



Input Filter

Use Lowpass filter and high-pass filter to attenuate high frequency and low frequency of the input signal.

Pre Delay

Use pre delay to adjust amount of the time between the direct signal and beginning of the early reflection signal. This parameter can be used to express size of the space. Reflection takes short time to bounce back in small room and it takes long time in large room. Also this parameter can be used to separate dry signal and reverb signal in the mix.

Modulation Speed

LFO Frequency dial controls speed of the modulation. When sync switch is turned on, LFO Frequency can be set as note value which is synchronized to the tempo. Valid range of the note value is automatically adjusted base on the current tempo.

Modulation Width

LFO Intensity dial controls width of the modulation and pre delay time dial controls center position of the modulation. Range of the LFO intensity is from 0 ms to +/- 10 ms.

Size and Decay

Size dial controls reverb time of late reflection and decay dial controls length of the reverb tail. Decay time can be used to express size of the space and material of the surface. Reflective materials, such as concrete or hardwood, gives longer decay time.

When auto size switch is turned on, size dial controls value of the parameters including size, pre delay, decay, damp, output LP frequency and early/late mix.

When sync switch is turned on in auto size mode, total reverb length, which can be controlled by pre delay, size and decay, is adjusted by note value which is synchronized to the tempo.

Damping

Damp dial controls amount of high frequency absorption for the late reflection signal. Low damping values produce brighter reverb sound and high damping values produces darker reverb sound.

Output Filter


Use lowpass filter to cut high frequency of the reverb signal.

Early / Late Mix

Adjust balance of the early reflection signal and late reflection signal from 0% (early reflection) to 100% (late reflection).


Equalizer

Low Shelving




Adjust frequency of the filter from 21 Hz to 1092 Hz.
Adjust gain from minus infinity to +12 dB
When gain is turned fully anti clock wise, the filer becomes high pass filter.

Mid Peak / Notch



Adjust frequency of the filter from 151 Hz to 2389 Hz.
Adjust gain from -14 dB to +14 dB
Bandwidth is fixed to one octave.

High Shelving




Adjust frequency of the filter from 296 Hz to 21096 Hz.
Adjust gain from minus infinity to +12 dB
When gain is turned fully anti clock wise, the filer becomes low pass filter.

Compressor

Overview

The compressor reduces dynamic range of audio signal. This is achieved by feedback topology as shown in the diagram below.




High pass filter is applied to the input of the side chain and the signal is routed to the gain stage in the side chain. The output of the gain stage is routed to the level detection. The level detector detects level of the input signal and generates control signal based on the level of the gain reduction required. The control signal is routed to the amplifier in the gain stage in the side chain to adjust level of the input signal from the high pass filter. The same control signal is also routed to the amplifier of the main gain stage to adjust level of the input signal.

The feedback topology is common in early analog compressors. Although there are several disadvantages to this topology, it is considered more musical than feed-forward design used in modern compressors. The feedback loop is implemented without unit delay to emulate behavior of the analog circuit.


Threshold and Ratio

When level of the input signal passes above the threshold, the input signal is compressed by the ratio.




Attack and Release

Attack is the time it takes for the signal to be compressed by the given ratio. Release is the time it takes the gain reduction to return to zero.






In this example, attack is 1 ms and release is 0.6 s. The initial transient pass through the compressor without gain reduction. It takes a while for the gain reduction to return to 0 dB after the input signal goes below the threshold.



Fast attack makes compressor to start gain reduction immediately after the input signal passes above the threshold. Slow attack, on the other hand, allows many of the transients to pass through compressor without gain reduction.

The figures below illustrate characteristic of the attack and the release. 1KHz Sine wave is used as an input signal (shown as transparent background images). It shows how compressor reacts with various combination of the attack and release settings.



Auto Release uses two time constants for the peak detector. It will react differently for the short transients and the long sustained sound.

Fast attack reduces the level of the transients and make sound soft, slow attack allows transients to pass through and gives a punch to the sound.

Fast release causes pumping and breathing effects. Slow release continues to reduce level for a long period of time after compressing louder part of the sound.


Side Chain High Pass Filter

-6 dB / octave high pass filter is applied to the input signal of the side chain. Frequency range is from 20 Hz to 185 Hz. This filter removes low frequency information from the input signal for the level detector to control excessive gain reduction and pumping effect.

Makeup Gain


Use Makeup to compensate the gain reduced by the compressor. The range is from 0 dB to 20 dB. Gain reduction meters show the amount of the gain reduction. You can used the information to adjust level of the makeup gain.

Gain Reduction Meter



Gain reduction meters shows peak level of the gain reductions in dB.

1. Gain reduction for the left channel
2. Gain reduction for the right channel



Input Gain

Adjust gain of the input signal routed to the compressor. The range is from -20 dB to 20 dB. When level of input signal is increased, GR meters show gain reductions even if threshold is set to 0 dB.


Dry / Wet

Use Dry / Wet to mix uncompressed signal (dry) and compressed signal (wet). Parallel compression technique, also known as New York compression can be achieved by adjusting amount of the wet signal mixed with the dry signal. When set to 0%, output is the dry signal. When set to 100%, output is the wet signal. When set to 50%, equal amount of the dry and the wet signal are mixed for the output.


Peak Limiter

Peak Limiter is an analog style limiter and provides clean sounding output signal. This limiter is not a lookahead brick wall limiter, so that it can't offer brick wall limiting. However it does not introduced any latency to the output signal.

Frequency response of the peak limiter is illustrated in the figure below. Output signal shows the result of 1 dB gain reduction.



Keyboard



Select Keyboard




Tap keyboard button in tool bar to show keyboard.

Select Key Range




Use plus / minus buttons to adjust range of the keyboard. Indicator shows lowest note of the keyboard.

Use Modulation Wheel




Adjust amount of the modulation when Mod Wheel is selected in modulation source.

Use Pitch Wheel




Adjust pitch of the oscillators. Range is plus / minus one octave.

Set Velocity




Use plus / minus buttons to adjust velocity.

Use Key Hold




Tap to Enable/Disable Key Hold.


Show Double Keyboard



Tap this button to show Double Keyboard.




Sequencer



Clip Editor



Each clip contains note event and parameter automation events for length of 16 bars. Maximum number of clips are 8.



Load Clip

Tap load button to load clip to make it active.

Play/Stop Clip

Tap play button to play/stop clip.

Edit Piano Roll

Tap edit button to open piano roll editor.


Add edit button

Tap plus button to add edit button.

Set Loop Mode

Tap this button to enable/disable loop mode. When loop is off, tap square icon to select a clip to play next.

Piano Roll Editor



Select Time Range and Loop Length

Use “Time Range Selector” to select Time Range for editing and Loop Length. On iOS, pinch gesture control zooming and drag gesture control scroll position.

To set Loop Length, tap on Loop Length button to show menu and select “Set Loop Length”. Right click on selector on Mac also show the menu.

Select Note Range

Use “Note Range Selector” to select note range for editing. On iOS, pinch gesture control zooming and drag gesture control scroll position.

Add Note

Double tap to add a note.

Delete Note

Select note and select Delete from context menu.

Scale Menu

Press and hold (right click on macOS) editor to show scale menu. Tap on scale button also shows the menu.

Edit Menu

Press and hold (right click on macOS) selected note to show edit menu.

- Chromatic
- Heptatonic**
- Ionian(Major)
- Dorian
- Phrygian
- Lydian
- Mixolydian
- Aeolian(Minor)
- Locrian
- HermonicMinor
- MelodicMinor
- C
- C#/Db
- D
- D#/Eb
- E
- F
- F#/Gb
- G
- G#/Ab
- A
- A#/Bb
- B

Chromatic Scale

Select Chromatic to edit notes in Chromatic Scale (12 tones).

Heptatonic Scale

Select Heptatonic to edit notes in Diatonic Scale, Harmonic Minor Scale or Melodic Minor Scale (7 degrees).

Root Key

Select a root key, when editing note in Diatonic Scale, Harmonica Minor or Melodic Minor Scale.

- Set Length
- Manual
- Maximum
- Whole
- Half
- Quarter
- 8th
- 16th
- 32nd
- Triplet Quarter
- Triplet 8th
- Triplet 16th
- Triplet 32nd

- Quantize
- Whole
- Half
- Quarter
- 8th
- 16th
- 32nd
- Triplet Quarter
- Triplet 8th
- Triplet 16th
- Triplet 32nd

- Hide Velocity

- Copy
- Paste
- Delete

Set Length

Select an option to set note length.

Quantize

Select an option to quantize note.

Set Velocity

Open velocity editor to edit note velocity.

Copy

Copy selected notes.


Paste

Paste notes.

Delete


Delete selected notes.

Velocity Editor




1. Select a note and open context menu.
2. Select "Set Velocity" in context menu
3. Select velocity sliders and adjust the velocity. Indicator in side bar shows maximum velocity in the selection. Maximum velocity value can be adjusted by plus and minus button and slider of the indicator.

Parameter Automation Editor



1. Tap plus button to show parameter list.
2. Select a parameter to edit.
3. Press and hold (right click on macOS) on parameter name to show context menu. Tap Delete to delete the parameter form editor.



4. Double tap to add an edit point.
5. Select edit points and press and hold (right click on macOS) on editor to show context menu.
6. Select Reset from context menu to reset the parameter.
7. Select Disable to inactivate automation.

Play Sequence

1. Set host sync

Tap sync button in transport bar to enable / disable sync mode.

When sync mode is enabled,

Stand Alone

Sequencer is synced to the clock provided by container application. The container application can use Ableton Link to synchronized with the Link enabled devices. Use buttons in transport bar to play / stop sequence and change tempo.

Plugin

Sequencer is synced to the clock provided by the host application. Use transport switches of the host application to play / stop the sequence and change tempo.

When sync mode is disabled,

Sequencer is driven by internal clock. Use buttons in transport bar to play / stop the sequence and change tempo.

2. Set tempo

Tap plus / minus button at the tempo section in the transport bar to open tempo slider. Tempo can be adjusted by the plus / minus buttons and the tempo slider. Tempo slider can adjust tempo by range of plus/minus 20 BPM. Double tap on the slider set center position to the current tempo value. Alternatively tapping on tempo indicator allows you to type in tempo value by computer keyboard.

3. Set loop

Use Time Range Selector to set loop length.

4. Set swing

Tap swing button in transport bar to show swing menu. Select an option from the menu to apply the swing.

Swing Type	Delay time	Duration (Ratio)	Note
Swing 0/6	0 (no swing)	50%	Straight
Swing 1/6	1/6 of 16th note	54%	Soft swing
Swing 2/6	2/6 of 16th note	58%	Soft swing
Swing 3/6	3/6 of 16th note	62%	Soft swing
Swing 4/6	4/6 of 16th note	66%	Triplet swing
Swing 5/6	5/6 of 16th note	70%	Hard swing
Swing 6/6	16th note	75%	Dotted hard swing

Delay time is an amount of delay applied to the third 16th note when a beat is divided by four 16th notes.

Duration (ratio) is a ratio of duration from the first 16th note to the third 16th note when a beat is divided by four 16th notes.

Amount of delay for the notes in a beat changes proportionally.

5. Set metronome switch

Tap metronome button in transport bar to enable / disable metronome.

6. Play

Tap play / stop button in transport bar or transport switches of the host application to play / stop the sequence.

Record Sequence

1. Set recording mode

Tap record button in transport bar to enable recording mode.

2. Play sequence

Play the sequence by following the steps described above. Recording will start after count-in. When tap recording button while playing, recording start without count-in. To start recording without count-in, play sequence first then tap record button.

3. Record notes

Play keypads or MIDI keyboard to record notes. Notes are automatically quantized at 16 step position.

4. Record parameters automation

Before recording parameter values, use edit command “Reset to Dial Value” to reset values of the parameter to the rest position.

Turn a dial or switch to record the parameter values. The color of the control changes to green to indicate the parameter is recorded. The control won't move automatically until disabling the recording mode in order to move the control freely during the recording.

If the synth or the effects is not producing sound, parameter value will not be recorded.

5. Stop recording

Tap record button in transport bar to disable recording mode or tap play button to stop playback.

Preset

User Preset contains values of the synth parameters and the sequence data. When loading a user preset, value of the synth parameters and the sequence data are both changed. User Presets can be saved in iCloud Drive or in AUv3 plug-in on the device.


To save user preset in iCloud drive, select Save in File Menu. User Presets in iCloud Drive can be accessed from iPhone, iPad or Mac.

To save user preset in plug-in, tap Add button in Preset Browser. Plug-In Preset is stored on the device and can be accessed from any host application which support AUv3 User Preset.

Factory presets contains only values of parameters of the synth and the effects. It doesn't contain any sequence data. When loading the preset, it will change the value of the parameters but sequence data remains the same.

To load factory presets, select a preset in Preset Browser.

File Menu



New...

Reset parameters and sequence data.


Open...

Open a preset from iCloud drive.

Save

Save a preset in iCloud drive.

Preset Browser



Load Factory Preset

Select a category from a list in the side bar. Tap on the name of the preset in Factory Preset Section to load.


Load User Preset

Select a category from a list in the side bar. Tap on the name of the preset in User Preset Section to load. If “Load Synth Param Only” is on, only synth parameters will be loaded. If the option is off, synth param and sequencer data will be loaded.

Delete User Preset

Tap and hold (right click on macOS) on the name of the preset in User Preset Section to show context menu and select Delete.

Save User Preset




Select a category from a list in the side bar. Tap on plus button to add a user preset.

Backup/Restore User Presets stored in the device



To back up or restore all user presets, tap on the iCloud icon to show export menu.



Select Export Presets to back up all of the user presets to iCloud.

Select Import Presets to import saved presets from iCloud.


Close File Browser



Tap on X icon to close the browser.

Setting Panel

General



Full Screen

Enable this option to open User Guide in full screen (full window size on macOS).

Open User Guide

Tap this button to open User Guide


Open Host Setting

Tap this button to open Stand Alone Settings

Version

Indicate version number of the installed app.

MIDI Global



MIDI Thru

When MIDI thru is turned on, MIDI messages received in MIDI input will be send out from MIDI output. This setting is required when connected device's local switch is turned off.

MIDI Monitor

Enable / disable MIDI key input monitoring. Key Range of keyboard and sequencer is automatically adjusted based on the input note.

Musical Typing

Enable / disable computer keyboard to play MIDI notes.


All Notes Off

Send note off message to all notes.

Map MIDI CC

Open or Close Map MIDI CC view.

MIDI Synth1



OMNI

Turn this on to connect all channel.

Input

Select input channel

Output

Select output channel

MIDI Local

When sending and receiving MIDI, connected device may send back the MIDI. This causes each notes to play twice. If this problem occurs, turn MIDI Local Switch OFF to disconnect User Interface from the audio engine.

MIDI Send

Enable / disable MIDI output.

MIDI Receive

Enable / disable MIDI input.

Min


Set min value of MIDI note input.

Max

Set max value of MIDI note input.

Stand Alone Setting

AbletonLink



Ableton Link is a new technology that synchronizes beat, phase and tempo of Ableton Live and Link-enabled iOS apps over a wireless network. It lets you play devices together with the freedom of a live band. Anyone can start and stop their part while others keep playing, and anyone can adjust the tempo and the rest will follow. You can use Link to play with several instances of Ableton Live, with Live and iOS apps, or even without Live in your setup: using Link-enabled apps on multiple devices, or multiple apps on the same device.

Ableton Link

Switch on to enable Ableton Link.

In-app notification

Switch on to displays a message when an Ableton Link enabled app is connected.

Sync Start/Stop


Switch on to synchronize start and stop with connected apps.

Connected Apps

Indicate number of currently connected apps.

Ableton Link requires Wireless Local Network Connections. Your device and other Link-enabled devices must be connected to the same local network.

Export Audio



Save As

Specify name of the audio file to export.

Location

Select location for the audio file to be stored. Options are Local or iCloud.

Length (Bars)

Length of the audio to be recorded. Specify the length by number of bars.

File Type

Select file type of the audio file. Options are AIFF, WAV, CAF and ACC.

Sample Rate

Select a sample rate of the audio file. Options are 44.1KHz, 48KHz, 88.2KHz and 96KHz.

Bit Depth

Specify bit depth of the audio file. Options are 16 bit, 24 bit and 32 bit.


Export

Tap export to export audio file.

Cancel

Tap cancel to return to the home page of the setting panel.

General



Run in Background

Turn this switch on to allow app to play continuously when the app enters in the background.

Resume Headphone Removed

Turn this switch on to allow app to play continuously when headphone is disconnected.

Hardware Latency

When Ableton Link is enabled, playback is synchronized to the Link-enabled devices. If there is a latency, output signal may not be aligned with the beginning of the each step.


In order to adjust the latency, set time in milliseconds in Hardware Latency. This value is used to compensate the latency of the output signal.

The latency varies on audio Interface and sample rate. Default value is 12.5 millisecond (sample rate is 44.1KHz)

Frame Size

Frame Size (Buffer Size) is a number of samples contained in an audio buffer. Higher frame size increases system performance but increases latency. Lower frame size decrease latency but decreases system performance. If you experience a problem with system performance, set higher frame size to improve the performance. Default setting is 256.

MIDI



Input


Select MIDI input port

Output

Select MIDI output port


Bluetooth (BLE) MIDI

Central



Open Bluetooth MIDI Central, which list available bluetooth devices. Select a name to connect to the device.

Peripheral



Open Bluetooth MIDI Peripheral. Turn Advertise MIDI Service switch on to makes the device to be discoverable from the other Bluetooth MIDI devices.

Export Audio

Prepare for exporting audio

1. Stop playback

Make sure the playback is stopped.

2. Select the first clip to play

Open clip editor and select a clip which should be played at first.

3. Turn off metronome

Make sure that metronome is turned off.

Adjust export settings

1. Save As

Type in file name if necessary.

2. Length

Set total length of the recordings by number of bars. This length should include the length of the delay or reverb tail.

3. Location

Select location to save the file. Options are local and iCloud.

4. File Type

Select a file type. Options for linear PCM format are AIFF, WAV or CAF. For compressed audio file, choose AAC. If the exported audio file is going to be edited in a different application, it is recommended to choose linear PCM format.

5. Sample Rate

Select sample rate. Options are 44.1KHz, 48KHz, 88.2KHz and 96KHz.

6. Bit Depth


Select bit depth. Options are 16 bit, 24 bit and 32 bit. Higher number results in better quality. If the exported file is going to be used in a different application, make sure that the which bit depth of the selected file type is supported by the application. (* 32 bit may not be supported in some applications).

Export Audio File

Tap export button to generate audio file and save the file in the specified location. When exporting the file is completed, browser can be open to audition the exported file.

Map MIDI CC

Select Map MIDI CC from setting menu to show MIDI CC Map View.
Use synth button on tool bar to select synth or effect to map MIDI CC to the parameters.
Select Map MIDI CC from setting menu to close MIDI CC Map View.



To make a MIDI CC (Continuous Controller) assignment, Tap a button then turn a knob on MIDI controller. The first MIDI CC number detected will be assigned to the parameter.

When CC is assigned, the button shows the CC number. Alternatively, double tap on a button to type in CC number.

To cancel the assignment or to remove the mapping, tap the button.

Override Automation

When a parameter is controlled by MIDI controller, it is not possible to automatically override automation. To override, turn off automation switch of the parameter or turn the dial of the parameter on screen that will stop the automation and the parameter can be controlled freely by MIDI controller.

Program Change

Program Change is received as following.

Factory: Bank (CC#0) = 0, Sub (CC#32) = [0, 1], Program = [0, 127] => preset [0, 255]
Plugin: Bank (CC#0) = 1, Sub (CC#32) = 0, Program = [0, 127] => Preset Number

Presets stored in iCloud Drive can't be selected by the MIDI program change.

Use External MIDI Keyboard with Stand Alone

1. Open host setting
2. Select MIDI from side bar menu. Set input MIDI port and output MIDI port.
3. Close host setting
4. Select MIDI Synth1 from side bar menu. Make sure “Receive” switch is turned on. Adjust channel and note range.
5. To stop hanging note, select MIDI Global from side bar menu, Tap on “All Note Off”.

Undo / Redo



1. Tap Undo / Redo button. Tap Undo to undo previous operation. Tap Redo to redo previous undo operation.

* Some operation such as play, stop or record are excluded from undo / redo operation.

* On macOS, turn on “Musical Typing” to enable keyboard shortcut, command + z for undo and shift + command + z for redo.


macOS

Stand Alone on macOS supports menu bar, keyboard shortcuts, context menu and touch bar. AUv3 plug-in on macOS supports keyboard shortcuts and context menu.

Menu Bar



Application




Open a window to display version information.

Open Preference window.

Quit this application.

File



Reset all parameters and sequence data.

Open a preset from iCloud drive.


Save a preset to iCloud drive.

Edit




Edit Commands are enabled when typing text.

View




Enable/disable full screen mode.

Export




Open Export Audio Page in Setting Panel.


Window



Help




Preference



Enable Help Section

Enable this option to show Help Section on Full Screen Mode.



Disable State Recovery

When application is launched, state of the previous session is automatically loaded by default. Check this option to disable state recovery, so the application always start in default state.

Touch Bar (MacBook Pro)



1. Play / Stop


Tap to play / stop sequencer

2. Tempo


Adjust tempo. Range of the slider is from 20 BPM to 240 BPM.

Use Computer Keyboard as MIDI Keyboard

Enable Musical Typing option in setting.



Keys are mapped as shown in the figure below.



Change Octave

[O-] Press Z key to select one octave below.
[O+] Press X key to select one octave above.

Change Velocity

[V-] Press C key to decrease velocity.
[V+] Press V key to increase velocity.

Set Timbral

[T1] Press B key to select Layer.
[T2] Press N key to select Synth1.
[T3] Press M key to select Synth2.

Keyboard Shortcut

Command	Key	AUv3	Note
New	Command-N	N/A	
Open	Command-O	N/A	
Save	Command-S	N/A	
Undo	Command-Z	✓	
Redo	Shift-Command-Z	✓	
Cut	Command-X	✓	Available for Text Input
Copy	Command-C	?	
Paste	Command-V	?	
Delete	Command-Delete	?	
Select All	Command-A	?	
Enter/Exit Full Screen	fn-F	N/A	
Play/Stop	Space	?	
Change Focus	Tab	?	
List Up	Arrow-Up	?	
List Down	Arrow-Down	?	
List Select	Enter	?	


? : (AUv3) Availability is depends on the host application, which can disable these functions.

* Some of the keyboard shortcut will be available in the future version update.


AUv3 on Apple Garage Band (Mac)

Load Plug-in


1. Launch GarageBand.
2. Choose a project dialogue window appears. Select a project and click on Choose.




3. Choose a track type dialogue appears. Select Software Instrument and click Create.




4. Click Plug-ins in Track Section.




5. Click arrows at the right side of the blue button “E-Piano”.



6. Select AU Instruments > RTMS > VAPolyFM



7. If plug-in window doesn't displayed. Tap blue button.



Activate Plug-In

After loading VAPolyFM or opening a project file, DSP engine of VAPolyFM may not be running.


In order to start the DSP engine, please do one of the followings.

- Press Play button on GarageBand.
- Play MIDI notes from GarageBand.

To play midi note by computer keyboard, select “Window > Show Musical Typing” from menu bar of the Garage Band. While the Musical Typing window is displayed, type A for note C.

Offline Renering

To start Offline Rendering on Apple Garage Band, select Cycle Range and select “Share > Export Song to Disk” from menu bar of the Garage Band. Selected Cycle Range will be rendered.



The followings are a few tips for offline rendering on Apple Garage Band.

- Make sure to save your project before performing offline rendering.
- Audition before initiating offline rendering. In order to perform offline rendering, DSP engine of VAPolyFM needs to be running. Please press play on GarageBand and make sure that DSP engine is running.
- If you are using clips, add an empty clip at the end and set the length to INF. Garage Band will stop rendering when audio level is dropped to inaudible level. This helps to record tail of the delay or reverb effect.


Known Limitations

- DSP Engine doesn't start until a user presses play button or play MIDI notes on GarageBand.
- Touch Bar shows blanc screen when showing button menu or context menu.
- GarageBand doesn't record MIDI notes from keyboards or sequencer of the VAPolyFM plugin.


AUv3 on Apple Garage Band (iOS)

Load Plug-in


1. Launch Garage Band
2. Create a new song



3. Select External > Audio Unit Extension



4. Select VAPolyFM



Change Plug-in Window Size

Tap arrow icon to resize the plug-in window.




Record Notes


Tap record button and play keyboard.



Edit Notes




Select Edit from menu and edit notes. Tap “Done” to close the window.




Save Project

Tap document icon to save the song.




Host Sync

Tap Host Sync button to sync transport and tempo to host application.



To disable transport sync, tap and hold sync button and select “Disable Transport Sync” from menu.



System Interruptions (iOS)

It is important to aware that system may interrupt playback in the following situations. Please make sure to test and make a plan to handle the situations.

1. Incoming calls or activating Siri

When receiving an incoming call or when activating Siri, it interrupts playback and send App to background. In order to avoid it occurs, turn off the followings in the Setting App.

- Do Not Disturb > Do Not Disturb > turn on.
- Siri & Search > Listen for “Hey Siri” > turn off.
- Siri & Search > Press Home for “Siri” > turn off.

2. Connecting or disconnecting a headphone

Headphone output has own DAC⁶ and own sample rate. The sample rate may be different form the sample rate of the audio engine. What will happens when connecting or disconnecting a headphone depends on the sample rates.

If the sample rates are same, playback continues when headphone is connected. When headphone is unplugged, playback will stop. You can change this behavior by turn Resume when headphone is unplugged on in Settings.

If sample rates are different, when connecting headphone or when disconnecting headphone stops playback and system will re-configure audio engine for the new sample rate.

The sample rate of the audio engine is set by an application or an audio interface. For example, when connecting an iOS device to Mac using a cable that came with your device, Inter Device Audio and MIDI on macOS uses 44.1KHz but Quicktime player app on macOS uses 48KHz.

If you are planning to connecting or disconnecting headphone for monitoring during playback, please make sure to test and learn what will occurs.

3. Changing sample rate setting

As described above, if sample rate of the audio engine is changed for any reasons, playback stops.

4. Media Reset

Under rare circumstances, the system terminates and restarts its media services daemon. When it occurs playback stops.

5. Pressing the Home button or sending App to background

When app is sent to background by pressing home button, showing notification center or any other reasons, playback stops. You can change this behavior by turn Run in Background on in Settings.

Additional Settings

Followings are other settings in the Settings App which you may want to adjusted.

- Display & Brightness > Auto-Lock > set to Never
- Sounds > turn off all system sound
- Notifications > Show Previews > set to Never
- Home Screen & Dock > Multitasking > Gestures > turn off

If you have installed apps that may send you a notifications or may interrupt playback, make sure to adjust settings of the apps to disable the functions.

If you are using Ableton Link, make sure that Local Network in Privacy is turned on. If you are using Bluetooth MIDI, make sure that Bluetooth in Privacy is turned on.

⁶ Digital to Analog Converter

Specification

Synthesizer

8 voice polyphonic Hybrid synthesizer

FM Synthesizer

Sound Source: 6 operators, 32 algorithms

Envelope: 5 stage, adjustable time and level for each stages.

LFO: Triangle, Saw Down, Saw Up, Square, Sine, S/Hold, From 0.04Hz to 42.2Hz

Transpose: +/- 24 semi tones.

Master Tune: +/- 75 cents

VA Synthesizer

Oscillators

Continuously variable wave shape (triangle, sawtooth, square)

Sub: Square, one octave lower (oscillator 1)

Pulse width for triangle and square (oscillator 1)

Pulse width for square (oscillator 2)

Hard Sync (oscillator 1 to oscillator 2)

Keyboard on/off (oscillator 2)

Low frequency mode (oscillator 2)

Tuning +/- 24 semitones

Fine tuning +/- 50 cents (oscillator 2)

LFO

Wave shape: sine, saw, down saw, square, triangle, random

Frequency Range: From 0.04Hz to 42.2Hz

Amplitude modulation by ADSR envelope

ADSR Envelope

Attack time: From 1ms to 6 sec

Decay time: From 1ms to 10 sec

Sustain level: From 0 to 100%

Release time: From 1ms to 10 sec

Delay time: From 0ms to 10 sec

Key Follow: From 100% to 25% (envelope length)

Oscillator Modulation

LFO: frequency, shape, pulse width

Env: frequency, shape, pulse width

Xmod: frequency and shape

Ring: oscillator 1 output and oscillator 2 output

Frequency modulation mode: linear / exponential

Filter

High pass filter: -12 dB per octave

Low pass filter: -12 dB per octave, -24 dB per octave

Frequency modulation: ADSR, LFO, Key Follow

Routing: Cascade / Parallel

Amplifier

Envelope: ADSR / Gate

Amplitude modulation by LFO

Pan modulation by LFO

Controllers

Modulation Wheel, Pitch Bend Wheel

Arpeggio

Type: Up, Down, Up&Down. Random

Frequency: From 1 Hz to 20 Hz

Portamento (Glide)

Time: From 10 ms to 10 second

Sequencer

Steps: 16 steps per bar
Loop Length: from 1 bar to 16 bars
Clip: 8 clips
Tempo: from 20 BPM to 999 BPM
Host Sync: On and Off

Effects

Delay, Chorus, Flanger, Reverb, EQ and Compressor

Delay

Delay Time	Range from 20ms to 1200ms
Feedback	Range from 0% to 100%
Highpass Filter	Range from 20Hz to 500Hz
Lowpass Filter	Range from 1000Hz to 20000Hz
LFO Frequency	Range from 0.01Hz to 10Hz
LFO Intensity	Range from 0.0 to 1.0 (from 0ms to +/- 10ms)
Effect Switch	ON or OFF
Sync Switch	ON or OFF
Frequency Range	From 0Hz to 22.05KHz (effect)

Chorus / Flanger

Delay Time	Range from 1ms to 40ms (chorus), from 1ms to 13ms / 20ms (flanger)
Feedback	Range from 0% to 100% (flanger)
Highpass Filter	Range from 20Hz to 500Hz
Lowpass Filter	Range from 1000Hz to 20000Hz
LFO Frequency	Range from 0.01Hz to 10Hz
LFO Intensity	Range from 0.0 to 1.0 Chorus: from 0ms to +/- 1ms Flanger: from 0ms to 12ms / 19ms / 39ms
Effect Switch	ON or OFF
Sync Switch	ON or OFF
Effect Selector	Chorus or Flanger
Frequency Range	From 0Hz to 22.05KHz (effect)

Reverb

Input lowpass filter	Range from 1KHz to 20KHz
Input high-pass filter	Range from 20Hz to 500Hz
LFO Frequency	Range from 0.01Hz to 10Hz
LFO Intensity	Range from 0.0 to 1.0
Pre Delay	Range from 1ms to 100ms
Size	Range from 0% to 100%
Auto Size Mode	ON or OFF
Decay	Range from 0% to 100%
Damp	Range from 0% to 100%
Output Lowpass Filter	Range from 1KHz to 20KHz
Early/Late Mix	Range from 0% to 100%
Tempo Sync	ON or OFF
Effect Switch	ON or OFF

Equalizer

Low Shelving	Frequency Range	Range from 21Hz to 1092Hz
	Gain	Range from -INF to +12dB
	High Pass Filter response	12dB / Oct
Mid Peak / Notch	Frequency Range	Range from 151Hz to 2389Hz
	Gain	Range from -14dB to +14dB
	Bandwidth	1 octave
High Shelving	Frequency Range	Range from 296Hz to 21096Hz
	Gain	Range from -INF to +12dB
	Low Pass Filter response	12dB / Oct

Compressor

Input Gain	Range from -20dB to 20dB
Input High Pass Frequency	Range from 20Hz to 185Hz
Threshold	Range from -40dB to 0dB
Makeup Gain	Range from 0dB to 20dB
Ratio	2, 4, 10
Attack	0.01ms, 0.1ms, 0.3ms, 1ms, 3ms, 10ms, 30ms
Release	0.1s, 0.3s, 0.6s, 1.2s, Auto
Dry / Wet	Range from 0% to 100%

*Appearance and specification of the product are subject to change without notice.

Release Notes

What's new in version 1.0

- Initial release